

CP21xx Customization Utility

File Settings Advanced

Device Selection

CP2102 - 0001 Refresh

Device Configuration

Set IDs

Baud Rate Alias

High Baud Rate	Low Baud Rate	Actual Baud Rate	Desired Baud Rate
4294967295	2457601	1500000	1500000
2457600	1474561	1500000	1500000
1474560	1053258	1200000	1200000
1053257	670255	923077	921600
670254	567139	571429	576000
567138	491521	500000	500000
491520	273067	461538	460800
273066	254235	255319	256000
254234	237833	250000	250000
237832	156869	230769	230400
156868	129348	153846	153600
129347	117029	127660	128000
117028	77609	115385	115200
77608	64112	76923	76800
64111	58054	64000	64000
58053	56281	57554	57600
56280	51559	55944	56000

Program Device

Status Logging

Log Programming to File:

CP21xx Customization Utility

File Settings Advanced

Device Selection

CP2102 - 0001 Refresh

Device Configuration

Set IDs

Baud Rate Alias

High Baud Rate	Low Baud Rate	Actual Baud Rate	Desired Baud Rate
56280	51559	55944	56000
51558	38602	51173	51200
38601	28913	38400	38400
28912	19251	28812	28800
19250	16063	19200	19200
16062	14429	16000	16000
14428	9613	14397	14400
9612	7208	9600	9600
7207	4804	7201	7200
4803	4001	4800	4800
4000	2401	4000	4000
2400	1801	2400	2400
1800	1201	1800	1800
1200	601	1200	1200
600	301	600	600
300	57	300	300

Program Device

Status Logging

Log Programming to File: